


Download

1. Intericad T6:Window 8/10 modeling patch file:

- i. Download the patch file(.zip) [HERE](#). Unzip it when finished download.
- ii. Copy all the items inside the folder and paste it to : **C:InteriCADT6Acad**
- iii. The computer will prompt whether you want to merge the items with existing one. Click **YES** to continue.

2. InteriCAD patch file

- i. Download the InteriCAD patch file(.zip) [HERE](#). Unzip it when finished download.You will get the “**InteriCAD**” folder.
- ii. Copy the whole “**InteriCAD**” folder and paste it to : **Computer>Local Disk (C:)**
- iii. The computer will prompt whether you want to merge the “**InteriCAD**” folder with existing one. Click **YES** to continue.



- iv. Restart your computer and run InteriCAD software again. Done.

3. ATI RADEON patch file:

i. Please click the link below to download the ATI Radeon Patch file:

<sites/default/files/mgxvr.zip>

ii. After download, extract the file(mgxvr.dll) and paste it to your **Drive (C:)/InteriCAD/VR/System**


iii. Replace the existing mgxvr.dll.

4. Window 7/8/10 driver for software dongle:


i. Please click the link below to download the Window 7/8/10 driver for software dongle:

<http://ts-exim.com/sites/default/files/EliteIV%20driver%20intallation.zip>


ii. After download,you will get a zipped folder named “**EliteIV driver intallation.zip**”.





iii. Right click the folder and extract the files to desktop.



iv. Open the extracted folder, and double click the **InstWiz3.exe** file to begin installation.



v. Please follow the instructions below for installation:



Vi. Done.

5. DivX Plus codec:

Please click the link below to enter the DivX Plus codec(video compressor) download page:

<http://www.divx.com/en/software/download>

6. Xvid codec:

Please click the link below to download the Xvid codec(video compressor):

<http://downloads.xvid.org/downloads/xvidcore-1.3.2.tar.gz>

7. Shutting down InteriCAD 7000 auto live update feature.

- i. Download the patch file(.zip) [HERE](#). Unzip it when finished download.You will get the “**InteriCAD**” folder.
- ii. Copy the whole “**InteriCAD**” folder and paste it to : **Computer>Local Disk (C:)**
- iii. The computer will prompt whether you want to merge the “**InteriCAD**” folder with existing one. Click **YES** to continue.